Using IDA Pro's Debugger. © DataRescue 2005

This small tutorial introduces the main functionalities of the IDA Debugger plugin. IDA supports debugging of x86 Windows PE files, AMD64 Windows PE files, and x86 Linux ELF files, either locally or remotely. Let's see how the debugger can be used to locally debug a simple buggy C console program compiled under Windows.

The buggy program.

This program simply computes averages of a set of values (1, 2, 3, 4 and 5). Those values are stored in two arrays: one containing 8 bit values, the other containing 32-bit values.

```
#include <stdio.h>
char char average(char array[], int count)
{
 int i;
 char average;
 average = 0;
 for (i = 0; i < count; i++)</pre>
   average += array[i];
 average /= count;
 return average;
}
int int average(int array[], int count)
{
 int i, average;
  average = 0;
  for (i = 0; i < count; i++)</pre>
    average += array[i];
 average /= count;
 return average;
}
void main(void) {
 char chars[] = { 1, 2, 3, 4, 5 };
  int integers[] = { 1, 2, 3, 4, 5 };
 printf("chars[] - average = %d\n",
   char average(chars, sizeof(chars)));
 printf("integers[] - average = %d\n",
    int average(integers, sizeof(integers)));
}
```

DataRescue


Running this program gives us the following results:

```
chars[] - average = 3
integers[] - average = 1054228
```

Obviously, the computed average on the integer array is wrong. Let's use IDA's debugger to understand the origin of this error !

Loading the file.

The debugger is perfectly integrated with IDA: to debug, we must first load the executable in IDA, to create a database. The user can disassemble the file interactively, and all the information which he will have added to the disassembly will be available during debugging. If the disassembled file is recognized as valid (x86/ARM64 PE or x86 ELF) by the debugger, a Debugger menu automatically appears in IDA's main window.





Instruction breakpoints.

Once we located our *int_average()* function in the disassembly, let's add a breakpoint just after its prolog, by selecting the *Add breakpoint* command in the popup menu, or by pressing the F2 key.

| 🖬 IDA View-A | | | |
|----------------|---|--------------|----------------------|
| .text:0040117B | | | |
| .text:0040117B | * 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 | S U B R O | U T I N E ;;;;;;;;; |
| .text:0040117B | | | |
| .text:0040117B | ; Attributes: bp | p-based fram | e |
| .text:0040117B | | | |
| .text:0040117B | ; intcdecl in | nt_average(i | nt *array,int count) |
| .text:0040117B | int_average | proc near | ; CODE |
| .text:0040117B | | | |
| .text:0040117B | array | = dword ptr | 8 |
| .text:0040117B | count | = dword ptr | ØCh |
| .text:0040117B | | | |
| .text:0040117B | | push ebp | |
| .text:0040117C | | mov ebp | , esp |
| .text:0040117E | | push ebx | |
| .text:0040117F | | push esi | |
| .text:0040112 | D | | , [ebp+count] |
| .text:004011 N | | | , [ebp+array] |
| .text:004011 | Jump to address G | | , ebx |
| .text:004011 | Mark position Alt+M | | , eax |
| .text:004011 F | Edit function Alt+P | mp esi | , eax |
| ▲ | | | |
| | Hide - (PAVE NUM.) | | |
| × | Undefine U | | |
| | Add breakpoint F2 | | |



Now, we can start the execution. We simply open the debugger window by using the appropriate icon, and run the program until it reaches our breakpoint, by pressing the F9 key or clicking the *Start* button in the debugger toolbar.

| File Edit Junp Search View Debugger Options Windows Help Image: Search View Debugger Options Search Help Help Image: Sear | IDA - C:\IDA\Presentations\Debugger\bug.idb (bug.exe) | |
|---|---|---|
| 88481179 ; !!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!! | □ □ | |
| | 09401179 ; !!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!! | Image: |



The IDA View-ESP window now shows us the stack frame of the interesting functions. We easily locate the array argument of our *int_average()* function, pointing to the integer array in the calling function (*main()* function).

| 📑 ID. | A View-ESP | |
|---------|------------|---|
| ESP 🔁 | 0012FF50 | dd 40A144h ; Dí@ 🔺 |
| | 0012FF54 | dd 7FFD5900h , 🔮 |
| | | ; [BEGIN OF STACK FRAMME int_average PRESS KEYPAD |
| EBP > | 0012FF58 | dd offset ori_izir8C |
| | 0012FF5C | dd offset loc_4011F6 |
| | 0012FF60 | |
| | 0012FF64 | |
| | 0012FF64 | ; [END OF STACK FRAME int_average. PRESS KEYPAD " |
| | 0012FF68 | 0 ; |
| | 0012FF6C | dd 400088h ; ©á@ |
| TOTAL S | | ; [BEGIN & STACK FRAME main] PRESS KEYPAD "-" TO |
| ECX > | | integers dd 1, 2, 3, 4, 5 ; DATA XR |
| EUL + | 0012FF84 | |
| | 0012FF89 | db 0 ,0 ,0 ; |
| | 0012FF8C | off_12FF8C dd offset unk_12FFB8 ; DATA XR ▼ |
| | | |

Now, we can start the execution. We simply open the debugger window by using the appropriate icon, and run the program until it reaches our breakpoint, by pressing the F9 key or clicking the Start button in the debugger toolbar.

Watches.

Why not add a watch on this array, in order to observe the evolution of its values during the process execution ?

| IDA View-ESP | | |
|-----------------------|---|---|
| 0012FF6C | dd 40A0B8h ; ©á@ | |
| ECX 0012FF70 | ; [BEGIN OF STACK FRAME main. PRESS KEYPAD intemers dd 1 2 3 4 5 ; | DATA XREF: debug003:0012FF60 [†] o |
| | chars N Rename N 5 | |
| 0012FF89 | Jump immediate Enter | |
| 0012FF8C 0012FF90 | off_1 Jump in a new window Alt+Enter | DATA XREF: debug003:0012FF58 [†] o |
| 0012FF94 | Jump to xref to operand X | |
| 0012FF98 | ₩ Chart of xrefs to ©?Z | |
| 0012FF9C 0012FFA0 | Chart of xrefs from | |
| 0012FFA4 | * Array * (PAVE NUM.) h - | |
| 0012FFA8 | 0101 DAT Data D -2■ | |
| • | V Undefine U | |
| 🚥 Watch List | L Jump to IP | |
| debug003:0012FF70 ; [| | |
| debug003:0012FF70 | agers 🚾 Add watch ; DATA | XREF: debug003:0012FF60 [†] 0 |
| | <u>ν</u> | • |
| 4 | Y | Þ |



Address evaluation.

By analyzing the disassembled code, we can now locate the loop which computes the sum of the values, and stores the result in the EBX register. The [edx+eax*4] operand clearly shows us that the EDX register points to the start of the array, and that the EAX register is used as an index in this array. Thus, this operand will successively point to each integer from the *integers* array.

| IDA View-EIP | | | |
|--------------------|------|---------------|---|
| 0040118A | jle | short end_of | _100p |
| 0040118C | | | |
| 0040118C add_integ | | | 🚽 🗖 Debugger 📃 🗌 |
| ₽ → 0040118C | add | ebx, f edx+ea | 18*4 1 |
| 0040118F | inc | eax | |
| 00401190 | cmp | | eax*4]=1 |
| 00401192 | jg | | TTO , LBEGIN OF STACK FRAME main. PRESS KEYPA |
| 00401194 | | | F70 integers dd 1, 2, 3, 4, 5 ; |
| 00401194 end_of_lo | op : | 0012F | F84 chars db 1, 2, 3, 4, 5 |
| > 00401194 | mov | eax, ebx | EAX 00000000 |
| 00401196 | cdq | | |
| 00401197 | idiv | esi | EBX 00000000 L |
| 00401199 | mov | ebx, eax | |
| 0040119B | mov | eax, ebx | ECX 0012FF70 L debug003:integers |
| 0040119D | рор | esi | EDX 0012FF70 L debug003:integers |
| 0040119E | рор | ebx | □ □ □ □ □ □ □ □ □ □ □ □ □ □ □ □ □ □ □ |
| 0040119F | рор | ebp | ESI 00000014 |
| | | | |
| | | | EDI 10012FF84 Lidehun 883:chars |

Step by step and jump targets.

Let's advance step by step in the loop, by clicking on the adequate button in the debugger toolbar or by pressing the F8 key. If necessary, IDA draws a green arrow to show us the target of a jump instruction.

| 🗄 IDA View-EIP | | |
|-------------------------|-----|------------------------------|
| 0040118A | jle | <pre>short end_of_loop</pre> |
| 0040118C | | |
| | add | ebx, [edx+eax*4] |
| 6340118F | inc | eax 🍈 👘 🗍 🕨 🔢 🔳 🛛 🕮 💷 🖓 💷 🖓 |
| | cmp | esi, eax Threads |
| 00401194 | jg | short add integer 000000148 |
| 00401194 end_of_loop: | | General registers |
| > 00401194 885-84494 | mov | eax, ebx EAX 00000001 L |
| 00401196 | cdq | |



The bug uncovered.


Now, let's have a look at ESI's value. The EAX register (our index in the array) is compared to this register at each iteration: so, we can conclude that the ESI register is used as a counter in the loop. But, we also observe that ESI contains a rather strange number of elements: 14h (= 20). Remember that our original array contains only 5 elements ! It seems we just found the source of our problem...

| 📑 IDA View-EIP | | | |
|---|-------------------|-------------------------------------|-------------------|
| 0040118A 0040118C | jle | <pre>short end_of_loop</pre> |) |
| 0040118C add_integer: 0040118C 0040118F | add inc | ; ebx, [edx+eax*4] | ◆ Debugger |
| 00401190 EIP → 00401192 | cmp jg | eax esi eax snort add_integer | Threads |
| 00401194 00401194 end_of_loop: ▶ 00401194 | mov | esi=14h eax, ebx | General registers |
| 00401196 00401197 | cdq idiv | esi | EBX 00000001 |
| 00401199 0040119B 0040119D | mov mov pop | ebx, eax eax, ebx esi | ECX 00000000 L |
| 0040119E 0040119F | рор рор | ebx ebp | EDX 0012FF70 |
| 1 | | | EDI 0012FF84 |



Hardware breakpoints.

To be sure, let's add a hardware breakpoint, just behind the last value of our *integers* array (in fact, on the first value of the *chars* array). If we reach this breakpoint during the loop, it will indeed prove that we read integers outside our array. So, we setup a hardware breakpoint with a size of 4 bytes (classical size for an integer) in *Read* mode.




As foreseen, if we continue the execution, the hardware breakpoint indeed detects a read access to the first byte of the *chars* array. Remark that EIP points to the instruction following the one which caused the hardware breakpoint ! It is in fact rather logical: to cause the hardware breakpoint, the preceding instruction has been fully executed, so EIP now points to the next one.

| IDA View-EIP | | | × | ID. | A View-ESP | | |
|-----------------------|------|-----------------------------|-----------|-------|------------|-------------|-----------|
| 0040118C add integer: | | | | | 0012FF70 | ; [BEGIN OF | STACK FRA |
| r* 0040118C | add | ebx, [edx+eax*4] | \square | EDX > | 0012FF70 | integers | dd 1, |
| 0040118F | inc | eax | | EDI 🔁 | 0012FF84 | chars | db 1, |
| 00401194 | cmp | esi, eax | | | 2FF89 | | db 0 |
| - 00401192 | jg | <pre>short add_intege</pre> | | | 9912FF8C | saved_fp | dd |
| 00401194 | | | | | 0012FF90 | retaddr | dd |
| 00401194 and_of_loop: | | | | | 0012FF94 | | dd |
| > 00401194 | mov | eax, ebx | | | 0012FF98 | | dd |
| 00401196 | cdq | | | | 0012FF9C | | dd |
| 00401197 | idiv | esi | | | 0012FFA0 | | dd |
| 00401199 | mov | ebx, eax 🖌 | 1 | | 0012FFA4 | | dd |
| 0040119B | mov | eax, ebx 🖉 | | | 0012FFA8 | | dd 7 |
| 0040119D | рор | esi 🖊 | | | 0012FFAC | | dd 7 |
| 0040119E | рор | ebx | | | 0012FFB0 | | dd |
| 0040119F | рор | ebp 🖉 | | | 0012FFB4 | | dd |
| 004011A0 | retn | | | | 0012FFB8 | saved_fp | dd |
| 004011A0 int_average | endp | | | | 0012FFBC | retaddr | dd |
| | | | Ľ. | | | | l |
| | | | 비 | | • | | |



By looking at the disassembly, we see that the value stored in ESI comes from the count argument of our *int_average()* function. Let's try to understand why the caller gives us such a strange argument: If we open the Stack Trace window, we see a stack of all caller functions. Simply double click on the *main()* function, to jump to the caller code. With the help of IDA's PIT (Parameter Identification and Tracking) technology, we easily locate the *push 20* instruction, passing an erroneous count value to our *int_average()* function.



Now, by looking closer at the C source code, we understand our error: we used the *sizeof()* operator, which returns the **number of bytes** in the array, rather than returning the **number of items** in this array ! As, for the *chars* array, the number of bytes was equal to the number of items, we didn't notice the error...



IDA's debugger gives you access to all the segments of a debugged process's memory space, allowing you to use all of IDA's powerful features: you can apply structures to bytes in memory, draw graphs, create breakpoints in DLLs, ...

| 📑 IDA View-A | | × | न Program Segm | entation | | _ | |
|--|--|----|----------------|----------|----------|--------|------|
| KERNEL32.DLL:77E70000 | ; | ▲ | Name | Start | End | B. W. | X. 🔺 |
| KERNEL32.DLL:77E70000 | - Comment Avenue During data | | DSER32.DLL | 77E53000 | 77E54000 | R., W. | |
| | ; Segment type: Pure data ; Segment permissions: Read | | USER32.DLL | 77E54000 | 77E5F000 | R | |
| | KERNEL32 DLL segment byte p | | FREERNEL32.DLL | 77E70000 | 77E71000 | R | |
| KERNEL32.DLL:77E70000 | assume cs:KERNEL32 | | FREERNEL32.DLL | 77E71000 | 77ECA000 | B | Х. |
| KERNEL32.DLL:77E70000 | ;org 77E70000h | | KERNEL32.DLL | 77ECA000 | 77ECC000 | R., W. | |
| KERNEL32.DLL:77E70000 | dw 'ZM'; e_magic | | FREERNEL32.DLL | 77ECC000 | 77F2C000 | R | |
| KERNEL32.DLL:77E70000 | dw 90h; e_cblp | | 🗗 GD132.dll | 77F40000 | 77F41000 | R | |
| KERNEL32.DLL:77E70000 | dw 3; e_cp | | 🗗 GD132.dll | 77F41000 | 77F75000 | R | Х. |
| KERNEL32.DLL:77E70000 KERNEL32.DLL:77E70000 | dw 0; e_crlc dw 4; e_cparhdr | | 🗗 GD132.dll | 77F75000 | 77F76000 | R., W. | |
| KERNEL32.DLL:77E70000 | dw 0; e minalloc | | 🗗 GD132.dll | 77F76000 | 77F79000 | R | |
| KERNEL32.DLL:77E70000 | dw OFFFFh; e_maxall | | 🗗 ntdll.dll | 78460000 | 78461000 | R | . – |
| KERNEL32.DLL:77E70000 | dw 0; e ss | | 🗇 ntdll.dll | 78461000 | 784AF000 | R | Х. |
| KERNEL32.DLL:77E70000 | dw OB8h; e_sp | -1 | 🗗 ntdll.dll | 784AF000 | 784B1000 | R., W. | . 💌 |
| KERNEL32.DLL:77E70000 | dw 0; e_csum | Ξl | 1 | | | | ▶ |
| • | | | Line 30 of 47 | _ | | | |

The way the debugger reacts to exceptions is fully configurable by the user.

| Exception | 5 | | <u>- 🗆 ×</u> |
|--------------|------------------------------------|-------------|-----------------|
| Code | Name | Handled by | On resume 📃 🔺 |
| C0000005 | EXCEPTION_ACCESS_VIOLATION | Debugger | Run handled |
| 80000002 | EXCEPTION_DATATYPE_MISALIGNMENT | Application | Run unhandled |
| 80000003 | EXCEPTION_BREAKPOINT | Application | Run unhandled |
| 80000004 | EXCEPTION_SINGLE_STEP | Debugger | Run handled |
| C000008C | EXCEPTION_ARRAY_BOUNDS_EXCEEDED | Application | Run unhandled |
| C000008D | EXCEPTION_ Exception handling | × | Run handled |
| C000008E | EXCEPTION_ | | Run unhandled |
| C000008F | EXCEPTION_ Handled by | | Run unhandled |
| C0000090 | EXCEPTION Debugger | | Run unhandled |
| C0000091 | EXCEPTION_ C Application | | Run unhandled |
| C0000092 | EXCEPTION | | Run unhandled |
| C0000093 | EXCEPTION_ © <u>R</u> un handled | | Run unhandled |
| C0000094 | EXCEPTION_ O Run unhandled | | Run unhandled |
| C0000095 | EXCEPTION_ | | Run handled |
| C0000096 | EXCEPTION_ | | Run unhandled |
| C0000006 | EXCEPTION OK Cancel | Help | Run unhandled |
| C000001D | EXCEPTION | | Run unhandled |
| C0000025 | EXCEPTION_NONCONTINUABLE_EXCEPTION | Application | Run unhandled |
| COOOOOFD | EXCEPTION_STACK_OVERFLOW | Application | Run unhandled |
| C0000026 | EXCEPTION_INVALID_DISPOSITION | Application | Run unhandled 🖵 |
| | | | |
| | OK Cancel Help | Search | |
| | | | |
| Line 1 of 26 | | | / |

This debugger is thus the essential complement to IDA itself, allowing you to interactively disassemble and debug everything, everywhere.



This tutorial is © DataRescue SA/NV 2005 Revision 1.1

DataRescue SA/NV

40 Bld Piercot 4000 Liège, Belgium T: +32-4-3446510 F: +32-4-3446514

